


# Parefeux sous OMV



The screenshot shows the OpenMediaVault web interface for firewall configuration. The 'Pare-feu' tab is active, displaying a table of firewall rules for IPv4. The table includes columns for Direction, Action, Famille, Source, Port, Destina..., Port, Proto..., Options supplémentaires, and Commentaire. The rules are listed as follows:

| Direction | Action | Famille | Source         | Port | Destina... | Port | Proto... | Options supplémentaires                    | Commentaire                                 |
|-----------|--------|---------|----------------|------|------------|------|----------|--|---|
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | -    | Tous     | -i lo                                      | Autoriser le trafic local                   |
| OUTPUT    | ACCEPT | IPv4    | -              | -    | -          | -    | Tous     | -o lo                                      | Autoriser le trafic local                   |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | -    | Tous     | -m conntrack --ctstate ESTABLISHED,RELATED | Conservier les connexions déjà établies     |
| INPUT     | ACCEPT | IPv4    | 192.168.1.2    | -    | -          | -    | Tous     |  | Accès total à partir d'un poste particulier |
| INPUT     | ACCEPT | IPv4    | 192.168.1.0/24 | -    | -          | -    | ICMP     |  | PING en local                               |
| INPUT     | ACCEPT | IPv4    | 192.168.1.0/24 | -    | -          | 5000 | TCP      |  | Accès à OpenMediaVault                      |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 22   | TCP      |  | Autoriser SSH                               |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 80   | TCP      |  | Autoriser HTTP                              |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 443  | TCP      |  | Autoriser HTTPS                             |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 137  | UDP      |  | Samba : NetBIOS Name Service                |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 138  | UDP      |  | Samba : NetBIOS Datagram Service            |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 139  | TCP      |  | Samba : NetBIOS Session Service             |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 445  | TCP      |  | Samba : SMB/CIFS Service                    |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 53   | UDP      |  | DNS   |
| INPUT     | ACCEPT | IPv4    | -              | -    | -          | 53   | TCP      |  | DNS   |
| INPUT     | DROP   | IPv4    | -              | -    | -          | -    | Tous     |  | Interdire tout ce qui n'est pas autorisé    |

From: <https://www.fablab37110.chanterie37.fr/> - Castel'Lab le Fablab MJC de Château-Renault

Permanent link: <https://www.fablab37110.chanterie37.fr/doku.php?id=start:raspberry:nas:firewall&rev=1736575800>

Last update: 2025/01/11 07:10

